


# CHIGH KI INOCULANTI

KI SOYBEAN ERR TOM AA NODUMAX SHA U ZUWAN AA YIAGH TSEBELEE



1

Zuwa aai yenge i chighki Nodumax ki dedoo




2

Too kiaren I kuman er 10kg I soybean lu asange waghen, I kuma er bokoti u pent u lita 5 kwa tar nahan, nahan ushi u gema uhua shin kiagh, kilu loba kiki kum u sam la ua nyior shin min cii yo.



3

U ande gum Arabic ka zule kon uu u kenlu ken leeda la je la uhua u shin mgerem ma kuman er 100mls ude gum Arabic una shin mger una ndohol cii man ve a er tom ana ye. Ubuu wer mgerem meragh I lu mgerem ma tsen.



4

Haa sam lashin zule kon u ulu ken leeda la ka gum Arabic je la wungwa tsebeelee.



5

Bugh ikpachi I inoculate kure vuwer u noduMax shin sam u soybean tsebelee man na jighjigh wer sam la chichi cii nungwa shin mi.



6

Tsen soybean ken mure I kuma minity utaanu yemen ken pue (5-10) sha chii u wasen mte u yange sha mi jighjigh, chii veu loo ye.

**KWAGH SHA KWAGH U INOCULANTE KA VUWER KON UU U LU KEEN LEEDA LA JE LA**

- a. Inoculate hemba lun fese u zuah ami aa chigh ki (taki)
- b. Hanma yiagh kia chigh kposuposu ki vian ki, nahan certom aa chigh ki yiagh kilo jighlaa sha hama yiagh kitu loo yo.
- c. De bum kpachi la ga shaa akuma u eren tom a min
- d. Inoculate kpen tahar shien vater yange sha mi yo, nahan ver un ken yough.
- e. Sha er u kaa man u er tom aa chigh kin yo nenge, sha kpachi la

**MKEYOL U NODUMAX VUWER CHII UKEN LEEDA LA JE LA.**

1. NoduMax wasen atine a soybean sha u wanamise shin nyam.
2. Ngu a ser mdoo u soybean I kumaan er 40-50% nahan.
3. Panden chan I taki u yamen.
4. Ngu a lu shin nyam I kuma 100kg ken jir I tom zanzan.

